# **Data Structure Documentation**

## **DataSourceModel Class Reference**

Inheritance diagram for DataSourceModel:



#### **Public Member Functions**

- \_\_construct ()
- addDataSourceApp (\$userID, \$dataSource=NULL)
- addDataSourceProject (\$dataSourceID, \$projectID, \$askAccess)
- addFileUser (\$dataSourceID, \$userID, \$dataSourceUser)
- **deleteDataSource** (\$dataSourceID)
- **deleteUserDataSource** (\$userID, \$dataSourceID)
- deleteDataSourceProject (\$\dataSourceID, \$\projID)
- deleteAllDataSourcesUser (\$userID)
- deleteAllUsersDataSource (\$dataSourceID)
- deleteAllProjectsDataSource (\$dataSourceID)
- deleteAllDataSourcesProject (\$projectID)
- updateDataSource (\$dataSourceID, \$userID=NULL, \$dataSource=NULL)
- updateDataSourceUser (\$dataSourceID, \$userID, \$dataSourceUser=NULL)
- updateDataSourceProject (\$dataSourceID, \$projectID, \$askAccess)
- **getDataSource** (\$dataSourceID)
- getOwnedDataSources (\$userID)
- **getDataSources** (\$filter=NULL, \$and=false)
- getAccessibleDataSources (\$userID)
- getUserDataSources (\$userID, \$filter=NULL, \$and=false)
- **getDataSourceUsers** (\$dataSourceID, \$filter=NULL, \$and=false)
- **getProjectDataSources** (\$projecID, \$filter=NULL, \$and=false)
- **getDataSourceProjects** (\$dataSourceID, \$filter=NULL, \$and=false)

## **Constructor & Destructor Documentation**

\_\_construct()
\_\_construct() is the constructor which initiates the connection to the database

#### **Member Function Documentation**

addDataSourceApp ( \$userID, \$dataSource = NULL)

addDataSourceApp() is a method for adding a file

\$userID	is is the id of the owner of the data source
\$dataSource	is an array containing the informations about the data source
\$dataSource	['name'] (required) is the name of the data source
\$dataSource	['url'] (optional) is the access url to the data source (default value=NULL)
\$dataSource	['appli'] (optional) means if the id is an application (1) or not (0) =default
\$dataSource	['config'] (optional) could be, for exemple, a JSON app configuration file

\$dataSource	['visible'] (required) means if the data source have to be hidden (=2), visible
	(=1) or on demand (=0, default)

new data source id if insert succeeded and FALSE if not

## addDataSourceProject ( \$dataSourceID, \$projectID, \$askAccess)

addDataSourceProject() is a method to link a data source to a project

#### Parameters:

\$dataSourceID	(required) is the id of a data source
\$projectID	(required) is the id of the project
\$askAccess	(required) means if an access request is refused (2), if it is accepted (1) or if it
	is made $(0)$ = default

#### Returns:

TRUE if insert succeeded and FALSE if not

## addFileUser ( \$dataSourceID, \$userID, \$dataSourceUser)

addFileUser() is a method to add a data source for a user

#### Parameters:

\$dataSourceID	(required) is the id of a data source
\$userID	(required) is the id of a user
\$dataSourceUser	(required) is an array containing the informations of the type of access has a user for a data source
\$dataSourceUser	['read'] (required) means if a user may read a data source or not (0) = default
\$dataSourceUser	['modify'] (required) means if a user may modify a data source or not (0) = default
\$dataSourceUser	['remove'] (required) means if a user may remove a data source or not (0) = default
\$dataSourceUser	['askaccess'] (required) means if an access request is refused (2), if it is accepted (1) or if the request is made (0) = default

#### Returns:

TRUE if insert succeeded and FALSE if not

## deleteAllDataSourcesProject ( \$projectID)

deleteAllDataSourcesProject() remove all data sources for a specific project

#### Parameters:

Canain at ID	
sprojeciiD	

## Returns:

a boolean (TRUE if deletion has been applied, FALSE if not)

## deleteAllDataSourcesUser ( \$userID)

deleteAllDataSourcesUser() remove all data sources for a specific user

#### Parameters:

\$userID	

#### Returns:

a boolean (TRUE if deletion has been applied, FALSE if not)

## deleteAllProjectsDataSource ( \$dataSourceID)

deleteAllProjectsDataSource() remove all projects for a specific data source

•			
	\$dataSourceID		ĺ

a boolean (TRUE if deletion has been applied, FALSE if not)

## deleteAllUsersDataSource ( \$dataSourceID)

deleteAllUsersDataSource() remove all users for a specific data source

#### Parameters:

\$dataSourceID

#### Returns:

a boolean (TRUE if deletion has been applied, FALSE if not)

## deleteDataSource ( \$dataSourceID)

deleteDataSource() delete a data source based on its id

#### Parameters:

\$dataSourceID

#### Returns:

a boolean (TRUE if deletion has been applied, FALSE if not)

#### deleteDataSourceProject ( \$dataSourceID, \$projID)

deleteDataSourceProject() remove a data source for a specific project

#### Parameters:

\$dataSourceID	
\$projID	

#### Returns:

a boolean (TRUE if deletion has been applied, FALSE if not)

#### deleteUserDataSource ( \$userID, \$dataSourceID)

deleteUserDataSource() remove a data source for a specific user

## Parameters:

\$userID	
\$dataSourceID	

#### Returns:

a boolean (TRUE if deletion has been applied, FALSE if not)

## getDataSource ( \$dataSourceID)

getDataSource() this method returns a data source based on its id

## Parameters:

\$dataSourceID	data source id
----------------	----------------

#### Returns:

a data source with its informations

\$response['id'] is the data source id

\$response['owner id'] is the owner id

\$response['name'] is the name of the data source

\$response['url'] is the url of the data source

\$response['application'] 0 for file and 1 for application

\$response['configuration'] is the configuration File

\$response['visible'] default visibility attribute for user files (0=hidden, 1=visible, 2=on demand)

\$response['add\_date'] is the creation date of the data source in the database

## getDataSourceProjects ( \$dataSourceID, \$filter = NULL, \$and = false)

**getDataSourceProjects()** is a method for searching the projects linked with a data source in the database

## Parameters:

\$filter	is optional and is an array containing search criterions
\$filter['project_na	is optional and contains the name (can be partial) of searched project(s)
me']	
\$filter['ask_access'	is optional and contains the access state (0=on demand, 1=OK, 2=KO) to the
J	searched project(s)
\$filter['ask_date']	is optional and contains the date when asked an access to the searched
	project(s)
\$and	is optional and is an boolean which is FALSE (default behavior) for processing
	the search query with OR operators and TRUE for AND operators

## Returns:

an array of files (ordered by date)

#### See also:

getUserDataSources() for the data structure of returned projects

## getDataSources ( \$filter = NULL, \$and = false)

getDataSources() is a method for searching data sources in the database

#### Parameters:

\$filter	is optional and is an array containing search criterions
\$filter['file_name']	is optional and contains the name (can be partial) of searched data source(s)
\$filter['file_url']	is optional and contains the url (can be partial) of searched data source(s)
\$filter['application	is optional and contains 0 for file and 1 for application
7	
\$filter['visible']	is optional and contains the default visible attribute for other users (0=hidden,
	1=visible, 2=on demand)
\$filter['add_date']	is optional and contains date when the data source(s) was/were added
\$and	is optional and is an boolean which is FALSE (default behavior) for processing
	the search query with OR operators and TRUE for AND operators

## Returns:

an array of data sources (ordered by date)

## See also:

getFiles() for the data structure of returned data sources

## getDataSourceUsers ( \$dataSourceID, \$filter = NULL, \$and = false)

getDataSourceUsers() is a method for searching the users of a data source in the database

\$filter	is optional and is an array containing search criterions
\$filter['user_name'	is optional and contains the lastname (can be partial) of searched user(s)
j	
\$filter['user_firstn	is optional and contains the firstname (can be partial) of searched user(s)
ame']	
\$filter['access_stat	is optional and is a boolean which is for the access state (0 = asked, 1 OK, 2
e']	KO)
\$filter['ask_date']	is optional and contains date when the user asked an access to the searched
	data source
\$and	is optional and is an boolean which is FALSE (default behavior) for processing
	the search query with OR operators and TRUE for AND operators

an array of data source(s) (ordered by date)

#### See also:

getDataSourceFiles() for the data structure of returned files

#### getOwnedDataSources ( \$userID)

getOwnedDataSources() this method returns the data sources that belong to a user

#### Parameters:

\$userID	user id

#### Returns:

data sources with the firstname and lastname of the owner

\$response['id'] is the data source id

\$response['file name'] is the name of the data source

\$response['url'] is the URL of the data source

\$response['application'] 0 for file and 1 for application

\$response['configuration'] is the configuration File

\$response['visible'] default visibility attribute for user files (0=hidden, 1=visible, 2=on demand)

\$response['add\_date'] is the creation date of the data source in the database

### getProjectDataSources ( \$projecID, \$filter = NULL, \$and = false)

getProjectDataSources() is a method for searching the data sources of a project in the database

## Parameters:

\$filter	is optional and is an array containing search criterions
\$filter['file_name']	is optional and contains the name (can be partial) of searched data source(s)
\$filter['file_url']	is optional and contains the url of the searched data source(s) or not
\$filter['application ']	is optional and contains 1 if it's an application and 0 if not
\$filter['config']	is optional and contains the config file
\$filter['visible']	is optional and contains the default visible attribute for user data sources
	(0=hidden, 1=visible, 2=on demand)
\$filter['add_date']	is optional and contains the creation date of searched data source(s)
\$filter['access_stat	is optional and contains the access state (0=on demand, 1=OK, 2=KO) to the
e']	searched data source(s) or not
\$filter['ask_date']	is optional and contains the date when asked an access to the searched data
	source(s) or not
\$and	is optional and is an boolean which is FALSE (default behavior) for processing
	the search query with OR operators and TRUE for AND operators

#### Returns:

an array of data sources (ordered by date)

#### See also:

getProjectDataSources() for the data structure of returned data sources

#### getUserDataSources ( \$userID, \$filter = NULL, \$and = false)

getUserDataSources() is a method for searching the data sources of a user in the database

\$filter	is optional and is an array containing search criterions
\$filter['file_name']	is optional and contains the name (can be partial) of searched data source(s)
\$filter['f_read']	is optional and contains the right to read the searched data source(s) or not
\$filter['f_modify']	is optional and contains the right to modify the searched data source(s) or not
\$filter['f_remove']	is optional and contains the right to remove the searched data source(s) or not

\$filter['access_state']	is optional and contains the access state (0=on demand, 1=OK, 2=KO) the searched data source(s) or not
\$filter['ask_date']	is optional and contains the date when the user asked an access to the searched data source(s) or not
\$filter['file_url']	is optional and contains the url of the searched data source(s) or not
\$filter['application	is optional and contains 1 if it's an application and 0 if not
\$filter['config']	is optional and contains the config file
\$filter['visible']	is optional and contains the default visible attribute for user data sources
	(0=hidden, 1=visible, 2=on demand)
\$filter['add_date']	is optional and contains the creation date of searched data source(s)
\$and	is optional and is an boolean which is FALSE (default behavior) for processing
	the search query with OR operators and TRUE for AND operators

an array of files (ordered by date)

#### See also:

getUserDataSources() for the data structure of returned files

## updateDataSource ( \$dataSourceID, \$userID = NULL, \$dataSource = NULL)

updateDataSource() is a method for updating a specific data source

## Parameters:

\$userID	is is the id of the owner of the data source
\$dataSource	is an array containing the informations about the data source
\$dataSourceID	is the id of the data source
\$dataSource	['name'] (optional) is the new name of the data source
\$dataSource	['url'] (optional) is the new access url to the data source (default value=NULL)
\$dataSource	['appli'] (optional) means if the id is an application (1) or not (0) =default
\$dataSource	['config'] (optional) could be, for exemple, a JSON app configuration file
\$dataSource	['visible'] (optional) means if the data source have to be hidden (=2), visible
	(=1) or if it is accessible on request (=0)

#### Returns:

TRUE if update succeeded and FALSE if not

## updateDataSourceProject ( \$dataSourceID, \$projectID, \$askAccess)

updateDataSourceProject() is a method for updating the access of a project to a data source

## Parameters:

\$dataSourceID	contains the id of the the id of the data source
\$projectID	is the ID of the project
\$askAccess	(required) means if an access request is refused (2), if it is accepted (1) or if
	the request is made $(0)$ = default

#### Returns:

TRUE if update succeeded and FALSE if not

## updateDataSourceUser ( \$dataSourceID, \$userID, \$dataSourceUser = NULL)

updateDataSourceUser() is a method for updating the access of a user to a data source

\$dataSourceID	contains the id of the data source
\$userID	is the id of the user
\$dataSourceUser	['read'] (optional) means if a user may read a data source or not (0) = default
\$dataSourceUser	['modify'] (optional) means if a user may modify a data source or not (0) =
	default
\$dataSourceUser	['remove'] (optional) means if a user may remove a data source or not (0) =

	default
\$dataSourceUser	['askaccess'] (optional) means if an access request is refused (2), if it is
	accepted (1) or if the request is made $(0) = default$

TRUE if update succeeded and FALSE if not

# The documentation for this class was generated from the following file:

• DataSourceModel.php

# Index

INDEX